
23.260


ANPR - TRUCK SCALE




Vladimír Petrovič


23.260

CAMERA SETTINGS - ENTRY/EXIT







INFRARED GATE SETTINGS




TRAFFIC LIGHTS SETTINGS






WEIGHING MODE SETTING- AUTO SINGLE WEIGHING




AUTOMATIC MODE TWO WEIGHINGS DIFFERENCE




PROCESS DESCR. – AUTOMAT. WEIGHING


LIGHTS, IR, CAMERAS, SCALE DISPLAY


1. IDLE







2. IR DETECTION







3. INCOMMING VEHICLE






4. WAITING FOR STABLE






5. PLATE RECOGNITION






6. FINISHED - LEAVING THE SCALE







6. FINISHED – LEAVING THE SCALE





1. IDLE






WEIGHING SAVED- SINGLE WEIGHINGS

In single weighings mode is each weighing stored separately after each weighing with recognized vehicle plate and actual weight from this weighing. If no plate is recognized, system assigns default plate number as "??? ANPR ???" (You can edit / change it later manually)

ANPR Single weighings are saved as regular single weighings, but marked as ANPR internally. (Orange color)




JOINING TWO SAVED SINGLE WEIGHINGS MANUALLY


If there are for example two single weighings weighed separately as 1st and 2nd weighing, which belongs together, you can join them manually and create one final result.

How to do it:

Select first weighing from the two by right click with the mouse and select Join ANPR.




The first weighing is selected to the right > Weighing No. 1:




Do the same with the 2nd weighing, system will then recognize order of these weighings according the date and time of weighing and recalculate the final result.

JOINING RESULT

On printscreen below you can see the result of joining. Now, if everithing is as needed, press the **Join** button and save result as new weighing. The two previous are now hidden.



Joining result



Joined weighing

EDITING OF SINGLE WEIGHING

If there is a faulty recognition saved, you can still make modification and manually "repair" this measurement.

Select desired row in the grid and edit with standard way.

